

ATD & ATC Software

Software Eröffnungsbildschirm / Software Front Screen




Bitte Datenschnittstelle per „Data Collection“ auswählen

Please open the PC port by selecting „Data Collection“

ATD & ATC Software

Software Eröffnungsbildschirm mit einfachen Statistik Angaben

Software screen with up-front statistical data



Data Collection

collect system

Report No.
 Report Date
 Tested by
 Awaiting

Status	No.	Date & Time	Project Name	Value	Unit
☒					

☐ All

 records

Now is under collecting.....


Start der Datenübertragung durch Betätigung der Taste „Begin/Continue“

Start of data transfer by pressing „Begin/Continue“

ATD & ATC Software

Anzeige der Messergebnisse

Display of the measured values



Data Collection

Create a new report Begin/Continue Pause/Stop Delete Records Save Export to Excell file Export Report Print Report Close Window

Collect system

Report No. 100518085916 Report Date 18.05.2010 Tested by username1 In progress ->Note

Status	No.	Date & Time	Project Name	Value	Unit
☐	1	2010-05-18 09:00:44 AM	Magnetic type	246	um
☐	2	2010-05-18 09:00:46 AM	Eddy current type	421	um
☐	3	2010-05-18 09:00:47 AM	Eddy current type	425	um
☐	4	2010-05-18 09:00:49 AM	Eddy current type	421	um
☐	5	2010-05-18 09:00:50 AM	Magnetic type	245	um
☐	6	2010-05-18 09:00:58 AM	Eddy current type	420	um
☒	7	2010-05-18 09:00:59 AM	Magnetic type	248	um

☐ All Statistic on last 5 records Chart diagram

Statistic on all Max. Value 0 Min. Value 0 Standard Deviation 0 Mean Value 0

Welcom to use the data-collection software. Being in progress... 2010-05-18 09:01:03 AM


Nur für TF / TG - Only TF / TG series:

Zum Herunterladen der im Gerät gespeicherten Messdaten: Durch Druck der „READ“ Taste

Download of stored values in the instrument by pressing the “READ” buttom

ATD & ATC Software


Anzeige der Grafik / Display of the graph



ATD & ATC Software


Exportieren nach MS Excel

Export function to MS Excel



ATD & ATC Software

Anzeige der Excel Daten / Display of the Excel values



	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P
	Status	No.	Date & Time	Rückgängig	Project Name	Value	Unit									
1	True	1	2010-05-18 09:07:52 AM		Magnetic type	245	um									
2	True	2	2010-05-18 09:07:54 AM		Magnetic type	245	um									
3	True	3	2010-05-18 09:07:55 AM		Magnetic type	245	um									
4	True	4	2010-05-18 09:07:56 AM		Magnetic type	245	um									
5	True	5	2010-05-18 09:07:58 AM		Magnetic type	245	um									
6	True	6	2010-05-18 09:08:02 AM		Eddy current type	424	um									
7	True	7	2010-05-18 09:08:04 AM		Eddy current type	422	um									
8	True	8	2010-05-18 09:08:05 AM		Magnetic type	249	um									
9	True	9	2010-05-18 09:08:10 AM		Magnetic type	0	um									
10	True	10	2010-05-18 09:08:20 AM		Magnetic type	0	um									
11																
12																
13																
14																
15																
16																
17																
18																
19																
20																
21																
22																
23																
24																
25																
26																
27																
28																
29																
30																
31																
32																
33																
34																
35																
36																
37																
38																
39																
40																
41																
42																
43																
44																
45																
46																
47																
48																
49																

Viel Erfolg in der Verwendung !

All the best for your measurements !

Ihr / Your SAUTER Team